

**External Parameters
for Numerical Weather Prediction and
Climate Application
EXTPAR
v5_6
User and Implementation Guide**

Hermann Asensio / Martina Messmer / Daniel Lüthi /
Katie Osterried / Jonas Jucker

August 24, 2021

Contents

1	Overall Description	5
1.1	Input raw datasets	5
1.2	Output external parameters	6
2	Software modules	9
2.1	Overview	9
2.2	Hybrid Python-CDO structure	12
2.3	Summary	12
3	Fortran modules	14
3.1	<i>extpar_topo_to_buffer</i>	14
3.1.1	Short description of the subprogram <i>extpar_topo_to_buffer</i>	14
3.2	Used namelist files and data in-/output:	20
3.3	<i>extpar_landuse_to_buffer</i>	20
3.3.1	Short description of the subprogram <i>extpar_landuse_to_buffer</i>	20
3.3.2	Used namelist files and data in-/output:	24
3.4	<i>extpar_aot_to_buffer</i>	25
3.4.1	Short description of the subprogram <i>extpar_aot_to_buffer</i>	25
3.4.2	Used namelist files and data in-/output:	26
3.5	<i>extpar_soil_to_buffer</i>	26
3.5.1	Short description of the subprogram <i>extpar_soil_to_buffer</i>	26
3.5.2	Used namelist files and data in-/output:	28
3.6	<i>extpar_flake_to_buffer</i>	29
3.6.1	Short description of the subprogram <i>extpar_flake_to_buffer</i>	29
3.6.2	Used namelist files and data in-/output:	29
3.7	<i>extpar_consistency_check</i>	30
3.7.1	Short description of the subprogram <i>extpar_consistency_check</i>	30
4	Python modules	33
4.1	General workflow	33
4.2	<i>extpar_alb_to_buffer</i>	33
4.2.1	Short description of the subprogram <i>extpar_alb_to_buffer</i>	33
4.2.2	Used namelist files and data in-/output	34
4.3	<i>extpar_cru_to_buffer</i>	34
4.3.1	Short description of the subprogram <i>extpar_cru_to_buffer</i>	34
4.3.2	Used namelist files and data in-/output:	35
4.4	<i>extpar_emiss_to_buffer</i>	35
4.4.1	Short description of the subprogram <i>extpar_emiss_to_buffer</i>	35
4.4.2	Used namelist files and data in-/output:	35
4.5	<i>extpar_ndvi_to_buffer</i>	35
4.5.1	Short description of the subprogram <i>extpar_ndvi_to_buffer</i>	35
4.5.2	Used namelist files and data in-/output:	36
4.6	<i>extpar_era_to_buffer</i>	36
4.6.1	Short description of the subprogram <i>extpar_era_to_buffer</i>	36
4.6.2	Used namelist files and data in-/output:	36
4.7	<i>extpar_isa_to_buffer</i>	36
4.7.1	Short description of the subprogram <i>extpar_isa_to_buffer</i>	36
4.7.2	Used namelist files and data in-/output:	37
4.8	<i>extpar_ahf_to_buffer</i>	37
4.8.1	Short description of the subprogram <i>extpar_ahf_to_buffer</i>	37
4.8.2	Used namelist files and data in-/output:	37

5	Current limitations	37
5.1	General limitations	37
6	Namelist Input for Extpar	39
6.1	Namelist files	39
6.2	Grid definition	40
6.2.1	general	40
6.2.2	Icon	40
6.2.3	COSMO	41
6.3	Orography	41
6.4	Land Use data	43
6.5	Aerosol optical depth	44
6.6	Climatological 2m temperature	45
6.7	NDVI data	45
6.8	Soil data	45
6.9	Freshwater Lake data	46
6.10	Albedo data	46
6.11	ISA data	47
6.12	AHF data	47
6.13	Emissivity parameter	47
6.14	ERA parameter	47
6.15	Consistency check	48

This short overview of the 'EXTPAR' software describes the working environment and the necessary steps to generate external parameters for numerical weather prediction and climate applications. More detailed information on specific modules of extpar can be found in the technical and scientific documentation.

1 Overall Description

Numerical Weather Prediction (NWP) models and Climate models require geographical localized datasets like the topographic height of the earth surface, the plant cover, the distribution of land and sea and, dependent on the schemes used, a variety of other external parameters.

The EXTPAR software system (EXTPAR - External Parameter for Numerical Weather Prediction and Climate Application) is able to generate external parameters for the different models COSMO and ICON. The software can run on a UNIX or Linux system where the raw data is stored. It allows operators (experienced users) running the scripts to create new external parameters controlled by user specifications like the model domain.

The following steps are performed for the generation of external parameters:

1. The target grid has to be specified. The supported target grids are
 - Rotated and non-rotated longitude-latitude grid (COSMO)
 - Icosahedral Triangular grids (ICON) with optionally higher resolution in selected regions ('local zooming')
2. The different raw data sets are aggregated to the target grid considering all raw data elements which are within the target grid element. If the target grid has a higher resolution than the input grid on which the raw data is available either an interpolation is performed or the target grid is filled with the nearest neighbor, but sub-grid scale statistical calculations (e.g. subgrid scale variance of orographic height) are dismissed.
3. All the different external parameter sets have to be checked for consistency against each other. In case of conflicts default values are set automatically. In the NetCDF output, information on the input data and the processing software is given.

1.1 Input raw datasets

The information for the external parameters is aggregated from various raw datasets for land use data, orography or soil data, see table 1 for a detailed list of the raw datasets.

The input data for Extpar is stored in a git-LFS repository at <https://gitlab.dkrz.de/extpar-data/extpar-input-data>. Instructions for downloading the whole repository or updating with new datasets can be found in the git-LFS repository. For access to the input data repository, contact the current Extpar source code administrator.

1 Overall Description

Dataset	Source	Resolution
GLOBE orography	NOAA/NGDC	30"
ASTER orography (limited domain: 60°N - 60°S)	METI/NASA	1"
MERIT/REMA orography	Composite DEM	3" (90m)
Globcover 2009	ESA	10"
GLC2000 land use	JRC Ispra	30"
GLCC land use	USGS	30"
Ecoclimap 2 land use	Meteo France	30"
ESA CCI-LC	ESA	10"
DSMW Digital Soil Map of the World	FAO	5'
HWSD Harmonized World Soil Database	FAO/IIASA/ISRIC/ISSCAS/JRC	30"
NDVI Climatology, SEAWiFS	NASA/GSFC	2.5'
CRU near surface climatology	CRU University of East Anglia	0.5 degree
Aerosol Optical thickness	NASA/GISS (Global Aerosol Climatology Project)	4x5 degree
AeroCom Global AOD data	AeroCom Project	1 degree
MACC-II climatological AOD (2003-2012)	ECMWF	1.125 degree
MACv2 monthly AOD, SSA and ASY data	MPI, RHM	1 degree
CAMS monthly 3D-climatology		
11 types of aerosols	ECMWF, RHM	3 degree
Global lake database (GLDB)	DWD/RSHU/MeteoFrance	30"
MODIS albedo	NASA	5'
MODIS derived soil albedo values	Community Land Model 3.5	30'
CAMEL Emissivity	NASA	5km

Table 1: Input raw datasets

1.2 Output external parameters

The output fields with the external parameters are shown in table 2.

external parameter	short name	unit	raw dataset
geometrical height	HSURF	<i>m</i>	GLOBE/ASTER/ MERIT/REMA
geopotential of earth surface	FIS	$m^2 s^{-1}$	GLOBE/ASTER/ MERIT/REMA
standard deviation of subgrid scale orographic height	SSO.STDH	<i>m</i>	GLOBE/ASTER/ MERIT/REMA
anisotropy of topography	SSO.GAMMA	1	GLOBE/ASTER/ MERIT/REMA
angle between principal axis of orography and global E	SSO.THETA	1	GLOBE/ASTER/ MERIT/REMA
mean slope of subgrid scale orography	SSO.SIGMA	1	GLOBE/ASTER/ MERIT/REMA
surface roughness	Z0	<i>m</i>	GLC2000, GLOBE/ASTER/ MERIT/REMA
Slope aspect	SLOPE.ASP	deg	GLOBE/ASTER/ MERIT/REMA
Slope angle	SLOPE.ANG	deg	GLOBE/ASTER/ MERIT/REMA

1.2 Output external parameters

external parameter	short name	unit	raw dataset
Horizon angles (resolution from 15deg)	HORIZON	deg	GLOBE/ASTER/ MERIT/REMA
Skyview factor	SKYVIEW	-	GLOBE/ASTER/ MERIT/REMA
soil texture	SOILTYP	-	DSMW/HWSD
fraction of sand	FR_SAND	%	HWSD
fraction of silt	FR_SILT	%	HWSD
fraction of clay	FR_CLAY	%	HWSD
fraction of organic carbon	FR_OC	%	HWSD
bulk density	BULK_DENS	gcm^{-3}	HWSD
deep soil texture	SUBSOILTYP	-	HWSD
deep soil fraction of sand	SUB_FR_SAND	%	HWSD
deep soil fraction of silt	SUB_FR_SILT	%	HWSD
deep soil fraction of clay	SUB_FR_CLAY	%	HWSD
deep soil fraction of organic carbon	SUB_FR_OC	%	HWSD
deep soil bulk density	SUB_BULK_DENS	gcm^{-3}	HWSD
fraction land cover	FR.LAND	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
ground fraction covered by plants max (vegetation period)	PLCOV_MX	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
ground fraction covered by plants min (vegetation period)	PLCOV_MN	1	GLC2000/Globcover/ EcoClimap/ESA CCI-LC
ground fraction covered by artificial (ur- ban) areas	URBAN	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
ground fraction covered by evergreen for- est	FOR_E	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
ground fraction covered by deciduous for- est	FOR_D	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
skin conductivity	SKC	$Wm^{-1}K^{-1}$	Globcover/ESA CCI- LC
root depth	ROOTDP	m	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
leaf area index max(vegetation period)	LAI_MX	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
leaf area index min (vegetation period)	LAI_MN	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
plant resistance	PRS_MIN	sm^{-1}	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
long wave surface emissivity	EMISS_RAD	1	GLC2000/Globcover/ Ecoclimap/ESA CCI- LC
climatology of monthly leaf area index	LAI12	1	Ecoclimap

1 Overall Description

external parameter	short name	unit	raw dataset
climatology of monthly fractional plant cover	PLCOV12	1	Ecoclimap
climatology of monthly roughness length (vegetation and orography)	Z012	m	Ecoclimap
(monthly) normalized differential vegetation index	NDVI	1	SEAWIFS
Annual maximum of normalized differential vegetation index	NDVI_MAX	1	SEAWIFS
(monthly) proportion of actual value/maximum normalized differential vegetation index	NDVI_RATIO	1	SEAWIFS
(monthly) optical thickness from black carbon aerosol	AER_BC	1	GACP
(monthly) optical thickness from dust aerosol	AER_DUST	1	GACP
(monthly) optical thickness from organic aerosol	AER_ORG	1	GACP
(monthly) optical thickness from SO4 aerosol	AER_SO4	1	GACP
(monthly) optical thickness from sea salt aerosol	AER_SS	1	GACP
(monthly) aerosol optical thickness for RG92 spectral bands	AOT12	1	MACv2
(monthly) single scattering albedo for RG92 spectral bands	SSA12	1	MACv2
(monthly) asymmetry factor for RG92 spectral bands	ASY12	1	MACv2
(monthly) layer-integrated mass of Sea Salt with dry radius in the range 0.03-0.5 microns	Sea_Salt_bin1	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Sea Salt with dry radius in the range 0.5-5.0 microns	Sea_Salt_bin2	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Sea Salt with dry radius in the range 5.0-20.0 microns	Sea_Salt_bin3	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Mineral Dust with dry radius in the range 0.03-0.55 microns	Mineral_Dust_bin1	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Mineral Dust with dry radius in the range 0.55-0.9 microns	Mineral_Dust_bin2	kgm^{-2}	CAMS
(monthly) layer-integrated mass of Mineral Dust with dry radius in the range 0.9-20.0 microns	Mineral_Dust_bin3	kgm^{-2}	CAMS
(monthly) layer-integrated mass of hydrophilic Organic Matter	Organic_Matter_hydrophilic	kgm^{-2}	CAMS
(monthly) layer-integrated mass of hydrophobic Organic Matter	Organic_Matter_hydrophobic	kgm^{-2}	CAMS
(monthly) layer-integrated mass of hydrophilic Black Carbon	Black_Carbon_hydrophilic	kgm^{-2}	CAMS

external parameter	short name	unit	raw dataset
(monthly) layer-integrated mass of hydrophobic Black Carbon	Black_Carbon_hydrophobic	$kg\bar{m}^{-2}$	CAMS
(monthly) layer-integrated mass of Sulfates	Sulfates	kgm^{-2}	CAMS
(monthly) Pressure at base of layer	half_level_pressure	Pa	CAMS
Near surface temperature (climatological mean)	T_2M.CL	K	CRU
Lake Depth	DEPTH_LK	m	GLDB
Lake Fraction	FR_LAKE	1	GLDB
(monthly) albedo	ALB_DIF12	%	MODIS
(monthly) Near Infrared Albedo	ALNID	%	MODIS
(monthly) Ultra Violet Albedo	ALUVD	%	MODIS
soil albedo for dry soils	ALB_DRY	%	Community Land Model 3.5
soil albedo for saturated soils	ALB_SAT	%	Community Land Model 3.5
fraction of impervious surface area	ISA	1	NOAA or EEA
anthropogenic heat flux	AHF	Wm^{-2}	NOAA
subgrid-scale slope parameter	S_ORO	1	GLOBE, ASTER, MERIT/REMA
EMISS yearly maximum for climatology 1998-2003	EMISS_MAX	1	CAMEL
monthly mean EMISS climatology 1998-2003	EMISS	1	CAMEL
(monthly) proportion of actual value/-maximum normalized differential vegetation index	EMISS_MRAT	1	CAMEL

Table 2: Output external parameters

2 Software modules

2.1 Overview

The software EXTPAR is composed of thirteen autonomous programmes. Twelve programmes are responsible for aggregating a raw data to the target grid, which is specified by the user. The thirteenth program, the consistency check, is performed in the end. The executables are called `extpar_*.to.buffer`, whereas the star stands for `ahf` (anthropogenic heat flux), `aot` (aerosol optical thickness), `cru` (temperature climatology of the Climate Research Unit (CRU)), `landuse`, `topo`, `ndvi` (normalized difference vegetation index), `soil`, `flake` (fraction lake), `isa` (impervious surface area), `albedo`, `emiss` (emissivity) and `era` (ERA climatologies) respectively. In Fig. 1 a schematic representation of EXTPAR is drawn. For the sake of clarity only the topography and land-use path is shown. The same can be applied for the other ten raw data sets. For all these programs there exist namelists. Most of the namelists only contain the name and path of the raw data file and the name of the buffer file, which is later used for the consistency check, and the name of the output of the final external variables.

The software modules read from the following namelist files:

- INPUT_AOT
- INPUT_LU
- INPUT_ORO, INPUT_OROSMOOTH, INPUT_RADTOPO, INPUT_SCALE_SEP

2 Software modules

- INPUT_SOIL
- INPUT_FLAKE
- INPUT_grid.org
- INPUT_COSMO_GRID or INPUT_ICON_GRID
- namelist.py

The namelists 'INPUT_grid.org' and either 'INPUT_COSMO_GRID' or 'INPUT_ICON_GRID' are used in all the programs, as they contain the general information of the target grid to which the raw data should be aggregated. The namelist file 'namelist.py' is read by all Python programmes.




Figure 1: Schematic illustration of the software EXTPAR.

2.2 Hybrid Python-CDO structure

For three of the external parameters calculated by EXTPAR, namely albedo, NDVI, and the Hadley CRU climatologies, problems appeared with target resolutions much higher than the provided input data set resolutions. The problem is that not all target grid points get assigned a proper value when using the legacy Fortran code and interpolation method.

The algorithm used in the legacy Fortran modules aggregates source grid point values onto the target grid where the input data is finer than the target grid and uses bi-linear interpolation to fill the remaining grid points where the input data is sparser than the target grid. However, starting from a 5 km global resolution for the target grid, points can potentially get assigned unreasonable values because of the insufficiency of the bi-linear interpolation algorithm.

To resolve this issue, for Extpar Version 5.4 a rewrite of those Fortran modules in Python, using the more sophisticated interpolation methods from CDO with support for all grids was conducted. Because the interpolation methods implemented in CDO are faster than those in Fortran for large model grids, *emiss_to_buffer* is written in Python as well. A rewrite in Python only makes sense for Fortran modules that do simple calculations with the data. These calculations can easily be substituted with CDO-commands in the Python modules. For modules doing complex calculations and providing many namelist parameters the user can define, like *extpar_topo_to_buffer* or *extpar_landuse_to_buffer*, a rewrite in Python is not planned.

The interpolation algorithms selected are:

- **albedo** *distance-weighted average remapping*
- **NDVI** *first order conservative remapping*
- **CRU climatology** *distance-weighted average remapping*
- **emissivity** *first order conservative remapping*
- **ERA climatology** *first order conservative remapping*
- **AHF/ISA** *bilinear interpolation*

The description of the used algorithms can be found via the CDO documentation: (<https://code.mpimet.mpg.de/projects/cdo/embedded/cdo.pdf>).

2.3 Summary

The external parameters can be generated by using thirteen programs to aggregate the various raw datasets to the target grid and after this by calling the final program for the important consistency check.

1. In a first step, the target grid and other parameters have to be specified by the user in the run-script (see section 6.2 for the details).
2. Then the aggregation of the raw datasets listed in table 1 to the given target grid can be performed by calling following executables
 - *extpar_aot_to_buffer*
 - *extpar_cru_to_buffer*
 - *extpar_landuse_to_buffer*
 - *extpar_topo_to_buffer*
 - *extpar_ndvi_to_buffer*
 - *extpar_soil_to_buffer*
 - *extpar_flake_to_buffer*

- `extpar_alb_to_buffer`
- `extpar_isa_to_buffer`
- `extpar_ahf_to_buffer`
- `extpar_emiss_to_buffer`
- `extpar_era_to_buffer`

These programs generate intermediate NetCDF files ("buffer") with the aggregated data.

3. The executable

- `extpar_consistency_check`

reads in the buffer-files, performs an automated consistency check, and finally generates the output fields listed in table 2.

The task of the consistency check that is performed at the end is to find inconsistencies in the soil data, the lake data and the NDVI data. In the soil data problems may appear between the soil type and the land-use, in particular for water and ice grid elements. For the fraction lake, minimal and maximal lake depth must be introduced and some seas such as the Caspian and the Dead Sea as well as Lake Constance must be defined manually. For more information see chapter 3.7.

3 Fortran modules

3.1 extpar_topo_to_buffer

3.1.1 Short description of the subprogram *extpar_topo_to_buffer*

The program *extpar_topo_to_buffer* aggregates the orography of the GLOBE, ASTER, or MERIT/REMA dataset to the target grid.

Target grid definition

The first part of this program contains several routines that read the namelists defined in the run script (see chapter 6 for more information on the run scripts). The first routine (*init_target_grid*) collects all the information needed to define the target grid with an integrated routine that gathers the variables given in the namelist 'INPUT_grid_org'. The variable *igrid_type*, which can either be 1 ('ICON') or 2 ('COSMO'), is an integer switch to define the target grid.

Then a routine reads the namelist of the corresponding grid, which is either 'INPUT_ICON_GRID' or 'INPUT_COSMO_GRID', depending on the chosen grid type. The run script contains only one of the two namelists. This must be manually changed by the user. These namelists contain among other variables the resolution of the grid, the user specified domain and the location of the center of the grid (for closer information about the namelists compare chapters 6.2.2 - 6.2.3). This allows an exact definition of the target grid.

Subgrid-scale slope

The namelist INPUT_ORO contains the parameter *lcompute_sgs*, to determine whether SGS should be calculated from the respective raw topography data. Formerly this was done in a separate executable *extpar_sgs.to.buffer.exe*. From Release 5.3 onwards, the SGS calculation was incorporated into the executable '*extpar_topo_to.buffer*'. As an intermediate step, the SGS is written out to NetCDF, one separate file for each raw topography tile is required. In case the preprocessed SGS NetCDF are already available, setting the parameter *lpreproc_oro* = *.false.*, deactivates the preprocessing, but not the aggregation of SGS to the target grid. We recommend to only do the preprocessing for the GLOBE dataset, because the computational cost for the ASTER or MERIT/REMA dataset is very high and no validation has taken place for this dataset.

Topographic correction for radiation

In a second step, the namelist 'INPUT_RADTOPO' is read. It contains the information if the user desires the calculation of the topographical corrected radiation parameters or not. If the switch is set to *.TRUE.* a border is added to the COSMO domain, as the computations need grid points beyond the edges of the normal domain. For ICON an on the fly extension of the grid is not possible, leading to missing data at the boundaries. Therefore the namelist-switch *max_missing* defines the threshold for the allowed fraction of missingness. Although the topographical corrected radiation can be calculated for both ICON and COSMO grids, the two sets of fields cannot be considered as identical, because for ICON grids one assumes plain (non-tilted) grid-cells, whereas for COSMO one also takes into account self-shading and effects related to tilted-plains for the skyview-factor.

The number of horizons is specified in the namelist. For the COSMO-7 and COSMO-2 setup 24 horizons are recommended. The icon-only parameter *radius* defines the radial distance taken into account for the topographical corrected radiation parameters. To account for the anisotropic behaviour of longwave-radiation, the namelist parameter *itype_scaling* defines the power of the term $SIN(\text{horizon-angle})$ in the equation of the skyview-factor. Due to performance reasons, for ICON the parameter *min_circ_cov* determines how many grid-cells can be skipped on the circumference considered for the computations.

Raw topography data The namelist 'INPUT_ORO' gives the possibility to switch between two raw orographical data sets (GLOBE, ASTER, or MERIT/REMA). In contrast to the 90m-data of MERIT/REMA, it must be considered, that the 30m-data of ASTER are not completely downloaded and are therefore not globally available. The downloaded region extends from 60°N to 60°S and from 180°W to 180°E. It is not recommended to derive the topographical parameters from ASTER if the region is beyond 60 degrees north or south. The ASTER files are arranged as displayed in Fig. 2. As the computational time of the program *extpar_topo_to_buffer* depends mainly on the number of ASTER files that are read in, two new parameters are introduced in the namelist. These two parameters give the number of columns and rows of the used ASTER files. The filenames of the desired ASTER files must be given manually. Figure 2 gives an example on how to use these parameters in the case of COSMO-2. A similar approach is used for MERIT/REMA DEM as shown in Figure 3. The latitude range between 60-90 deg S is covered by REMA DEM, which was mapped to the MERIT data format by BKG, Germany. If GLOBE is used the columns and rows are set to 4 and all GLOBE files must be listed in the *topo_files* parameter. A check in the program *extpar_topo_to_buffer* is introduced, which gives a warning if the borders of the domain are exceeded. This is followed by an abortion of this program. As there is no need to calculate the subgrid scale parameters (SSO) for high resolution setups, there is the logical switch *lssoparm* to turn off the calculation of the SSOs.




Figure 2: Illustration of the single domains of the 240 ASTER tiles. An example of how the three parameters *ntiles_columns*, *ntiles_row* and *topo_files* in the namelist could look like is given in red.

Furthermore the variables of the namelist 'INPUT_ORO', which cover all the raw topographical data information, are fed into the program. In this namelist the path of the raw data is given as well as the names of the topography data files. An integer switch allows the choice between the highly resolved, non-global topography ASTER, the global but coarser MERIT/REMA and the coarser and

3 Fortran modules

global data set GLOBE (1: GLOBE, 2: ASTER, 3: MERIT/REMA). Furthermore the logical switch to decide whether the SSO parameters are desired or not is read. In order to define the right number of raw data tiles the variables `ntiles_column` and `ntiles_row` must be available in the namelist. Additionally, the names for the buffer and output files are defined.

The topography data files must be manually changed in the run script, when switching from GLOBE to ASTER, or MERIT/REMA and vice versa.

Then, the number of tiles of the raw topography data is defined (this varies between the raw data sets: 16 tiles for GLOBE, 1 - 240 tiles for ASTER, 72 tiles for MERIT/REMA). This value is the product of the number of tiles in each column and each row. The variables concerning the raw topography are allocated and in a further step filled with the according values. These values are the edges of each raw topography tile, the number of gridpoints in x- and y-direction, as well as the resolution in both directions. These are directly deduced from the raw data NetCDF files. Finally the borders of the ASTER domain are defined, when ASTER is used.

After the definition of the target grid and the topography set, a check examines the compatibility of the user specified input with the target grid; as ASTER is not globally available at the moment it is checked that the user specified domain is contained in the current ASTER domain. And, if this is not the case, the `extpar_topo_to_buffer` is aborted with an error message.

Scale separation input

The namelist `INPUT_SCALE_SEP` gives all the information needed to calculate the SSO parameters and roughness length based on a 3 km filtered topography. Thus the logical switch `lscale_separation` must be read to decide if a scale separation is desired or not. Furthermore the raw data files and path must be provided. Note that the `lscale_separation` can only be set to `.TRUE.` if GLOBE is used as topography, as there is no ASTER or MERIT/REMA based 3 km filtered topography available yet.




Figure 3: Illustration of the single domains of the 60 MERIT and the 12 REMA tiles below 60 deg S latitude.

Additionally the user must decide if the computation of the SSO parameters make sense or not. Table 3 can give some assistance to come to the right decision.

Resolution	Calculation of standard deviation	lscale_separation
Model resolution is smaller than raw data resolution	SSOs: $\sigma = 0$ z0: $\sigma = 0$.FALSE.
Model resolution is greater than the raw data resolution but smaller than 3 km	SSOs: $\sigma = 0$ z0: $\sigma = \sum (model - raw\ data)^2$.FALSE. and lssso_param = .FALSE.
Model resolution is greater than 3 km	SSOs: $\sigma = \sum (model - 3km\ filt)^2$ z0: $\sigma = \sum (3km\ filt - raw\ data)^2$.TRUE.

Table 3: Recommendations on the usage of the scale separation. Be aware that the actual model topography resolution is approximately twice as large as the model resolution. E.g. COSMO-2: The resolution of the topography is approximately 4 km.

Orographical smoothing input

The last namelist that must be read before allocating the orography is the namelist 'INPUT_ORO-SMOOTH', which defines all the variables needed to perform an orographical smoothing. The lfilter_oro logical switch, controls the computation of the smoothing in EXTPAR.

Aggregation of the raw topography to the target grid

The subroutine *det_topo_tiles_grid* defines the grid of each raw topography data tile. For this, the start and end latitude and longitude of each tile, the distance between two grid points in the latitudinal and longitudinal direction (dlat, dlon) as well as the number of grid points in both directions (nlat, nlon) are derived for each tile. Additionally, the grid for the whole GLOBE, ASTER, or MERIT/REMA domain is derived; This is done in the subroutine *det_topo_grid*.

Before the raw topography can be aggregated on the target grid, the target variables must be allocated. These variables include the land fraction (FR_LAND), the elevation of the surface (hh_target), the standard deviation of the elevation (stdh_topo), the roughness length of the topography (z0_topo), the sub-grid scale orography parameters (theta_topo, aniso_topo and slope_topo) and the topographical corrected radiation parameters (slope_asp, slope_ang, horizon and skyview). For the ICON grid some additional parameters must also be allocated.

The following paragraphs describe computations on the raw data grid.

The subroutine *agg_topo_data_to_target_grid* does the actual work of aggregating the raw topography to the target grid. The whole topographical data set is divided in bands of 500 grid points in the latitudinal direction and the whole range of the raw data domain in the longitudinal direction (compare for this the black band in Fig. 4). This band is introduced to optimize memory usage, as it is not possible to read the whole raw data in one pass. In order to read the correct raw data the start and end index of each tile (green crosses in Fig. 4) is defined. These indices are additionally associated with a start and end index (red circles in Fig. 4) inside the band. The definition of the two kinds of indices is performed by the routine *get_topo_tile_block_indices*. With this band the whole raw data is read step by step as suggested in Fig. 4. If the scale separation is desired the same procedure is applied to the 3 km filtered topography.

After this step, a temporary variable of elevation values is filled. This variable consists of three rows, which comprises the whole longitude range of the raw topography data. This is used to deduce the gradients of the topography, which are calculated as averaged differences between one eastern and one western grid point (x-gradient) or with one northern and one southern grid point (y-gradient). From these gradients in x- and y- direction also the squared gradients and the dx*dy are computed.




Figure 4: Schematic illustration of the filling of the raw data with a 500 grid points long band. The green crosses indicate the start end end latitudes and longitudes of each raw topography tile (light blue tiles), whereas the red circles show the indices inside the band, where the green indices of the tiles must be placed.

This is followed by a call of the subroutine *find_rotated_lonlat_grid_element_index*. This routine defines to which grid element of the target grid a certain grid element of the raw topography belongs. The allocation of the raw data points to the target grid element is performed as shown in Fig. 5 a). All raw data elements that are closer than half a grid point (green box) to the target point (red circle) are used to define the value at the corresponding target grid point. Only the green grid elements in Fig. 5 b) belong to a target grid element. The rest of the raw topography is unused.

The elevations of raw data pixels that belong to one target grid element are summed up, and the number of raw data pixels contributing to one target grid element is tracked. A summation of the raw data values for each target grid element is also performed for the squared elevation, which is later used for the standard deviation, and for the gradients calculated before, which are required for the computation of the subgrid scale orography parameters. The latter is only calculated if the SSO parameters are desired. When making use of the scale separation the squared differences between the original and the 3 km filtered topography must be computed at every grid point. This is needed in order to calculate the roughness length specific standard deviation. After these calculations, the temporary rows are shifted to the north and the computation is repeated for the next center line. As soon as a band of 500 rows is finished a new one will be read in.

Now that all auxiliary variables are available, all loops over the raw topography data are closed and a new one over all the grid points of the target grid is opened.

The following paragraphs describe computations on the target grid.

First of all the elevation is calculated as the mean of all the raw topography data points that are enclosed in one target grid point.

As soon as the topography is available on the target grid, the orographical smoothing is applied using the subroutine *do_orosmooth*.

In a next step the variance and the standard deviation of the elevation at each target grid point is estimated. Subsequently, the SSO parameters angle of principle axis, anisotropy factor and slope parameter are calculated according to Lott and Miller (1996). These SSOs are only calculated if the SSO




Figure 5: a) Illustration of the aggregation of the raw data to the target grid. The red circle indicates a target grid point, while the green rectangle represents the part of the raw data that is aggregated on the target grid point. b) Showing the target grid on top of the raw data set, where only the green grid points of the raw data are used for the target grid.

switch is set to `.TRUE.` and if the standard deviation of the height is more than 10 meters, as the trivial case of the ocean is tried to be avoided. If the scale separation is switched on the SSOs are based on the 3 km filtered topography. Finally the orographical roughness length is calculated using the standard deviation, but only if at least one raw data pixel is present in the target grid element.

In the case where no raw topography data pixel is available in a target grid, a weighted bilinear interpolation between neighboring raw data grid element is performed to obtain an elevation in all target grid points. This mainly happens if the raw topography has a similar resolution as the target grid. If the bilinear interpolation needs to be applied, all the SSO as well as `z0` are set to zero for this grid element. With this step the end of the subroutine *agg_topo_data_to_target_grid* is reached.

In the program *extpar_topo_to_buffer* an additional check on SSOs and `z0` is performed. If none of the elements of the target grid is associated with at least ten raw data pixels, or as soon as one single element is not associated with any raw data pixel, all the SSOs and `z0` are set to zero.

As soon as there is a value for all the target grid elements, the calculation for the topographical corrected radiation parameters can start, if desired at all.

Finally NetCDF files for the orography based external parameters are created, where different NetCDF

routines are used for each grid type, as different parameters are needed for each of them. If the `lrad-topo` is set to `.TRUE.` the enlarged domain is cut back to the user specified domain, before writing it to the NetCDF file.

3.2 Used namelist files and data in-/output:

- namelist files: `INPUT_grid.org`, `INPUT_COSMO_GRID`, `INPUT_ICON_GRID`, `INPUT_ORO`, `INPUT_OROSMOOTH`, `INPUT_RADTOPO`
- data input (GLOBE): `GLOBE_A10.nc` - `GLOBE_P10.nc`
- data input (ASTER): `ASTER_T001.nc` - `ASTER_T240.nc`
- data input (MERIT/REMA): `MERIT_N90-N60_E150-E180.nc4` - `REMA_BKG_S60-S90_W180-W150.nc4`
- data input (filtered): `GLOBE_A_filt_lanczos_window.nc` - `GLOBE_P_filt_lanczos_window.nc`, `GLOBE_A_filt_tukey_0.75_3.0_it4.nc` - `GLOBE_P_filt_tukey_0.75_3.0_it4.nc`
- Output: buffer file with orography data (`/orography_io_extpar/ orography_buffer_file`)
output file with orography data (used in `extpar_cru_to_buffer`)
(`/orography_io_extpar/ orography_output_file`)

3.3 `extpar_landuse_to_buffer`

3.3.1 Short description of the subprogram `extpar_landuse_to_buffer`

The executable `extpar_landuse_to_buffer` aggregates the land use data to the target grid. Four different raw datasets can be processed: Globcover, GLC2000, Ecoclimap-2, GLCC and ESA CCI-LC; as GLC2000 and Globcover do not include Antarctica, GLCC or ESA CCI-LC data can be used for the missing areas.

Target grid definition

The definition of the target grid is done by reading the namelist `'INPUT_grid.org'`. This namelist contains the information about the grid type, which can either be `ICON` or `COSMO`. With the information about the grid type, the namelist containing the grid definition can be read. The name of the namelist must be changed manually by the user, according to the chosen grid type. The namelist must either be `'INPUT_ICON'` or `'INPUT_COSMO'`. For a more exact description of the target grid definition, read the subsection *'Target grid definition'* in section 3.1. After specifying the grid definition the southern band of the target grid is defined. This information is important, as the two raw data sets GLC2000 and Globcover do not cover the region below 60 degrees south. If this region is desired by the user, the third data set must be considered for the domain below the southern band. Additionally the target fields for the land use data are allocated.

Raw landuse data

In a next step the namelist `'INPUT_LU'` is read. It contains an integer switch (`i_landuse_data`) that gives the possibility to choose between the four different raw data sets e.g., 1 (Globcover), 2 (GLC2000), 3 (GLCC) and 4 (Ecoclimap) 5 (ESA CCI-LC). For Globcover one can additionally choose to use the corine landuse dataset by setting the logical switch (`L_use_corine`) to `TRUE`. Furthermore the path and the filename of the desired raw data and of GLCC are specified there. The user must adjust the filename and path manually according to the chosen raw data in `i_landuse_data`. In addition the name of the desired lookup table is read, which again can be chosen by the user using an integer switch `lookup_table_lu`. This switch has no effect if the Ecoclimap dataset is chosen. The lookup tables are described in more detail in table 5. Finally, the names of the buffer files for the target landuse fields and for the target GLCC fields are specified.

After having read the namelists, the number of tiles of the raw data set is defined. The number of tiles is set to 1 as default and must only be changed for the raw data set Globcover or ESA CCI-LC, which are composed of 6 tiles. The basic information of the Globcover tiles, such as the latitude and longitude edges and the resolution is allocated according to the number of tiles. Later these variables are filled with the respective information, read from the NetCDF files directly.

For the remaining procedures the three different raw land use data have their separate routines, which are constructed identically.

The allocation of the data is done using the number of grid points in the latitudinal and longitudinal direction. Furthermore the land-use target fields are allocated using the target grid for the dimension size and the number of land-use classes. The land-use classes differ for the three raw data sets and are described in more detail in table 4.

Data Set (Total number of Classes)	Number of Class	Name of Class
GLOBCOVER (23)		
	01	irrigated croplands
	02	rainfed croplands
	03	mosaic cropland (50-70%) - vegetation (20-50%)
	04	mosaic vegetation (50-70%) - cropland (20-50%)
	05	closed broadleaved evergreen forest
	06	closed broadleaved deciduous forest
	07	open broadleaved deciduous forest
	08	closed needleleaved evergreen forest
	09	open needleleaved decid. or evergr. forest
	10	mixed broadleaved and needleleaved forest
	11	mosaic shrubland (50-70%) - grassland (20-50%)
	12	mosaic grassland (50-70%) - shrubland (20-50%)
	13	closed to open shrubland
	14	closed to open herbaceous vegetation
	15	sparse vegetation
	16	closed to open forest regulary flooded
	17	closed forest or shrubland permanently flooded
	18	closed to open grassland regularly flooded
	19	artificial surfaces
	20	bare areas
	21	water bodies
	22	permanent snow and ice
	23	undefined
Corine (23)		
	11	irrigated croplands
	14	rainfed croplands
	20	'mosaic cropland (50-70%) - vegetation (20-50%)
	30	mosaic vegetation (50-70%) - cropland (20-50%)
	40	closed broadleaved evergreen forest
	50	closed broadleaved deciduous forest
	60	open broadleaved deciduous forest
	70	closed needleleaved evergreen forest
	90	open needleleaved decid. or evergr. forest
	100	mixed broadleaved and needleleaved forest
	110	mosaic shrubland (50-70%) - grassland (20-50%)
	120	mosaic grassland (50-70%) - shrubland (20-50%)
	130	closed to open shrubland
	140	closed to open herbaceous vegetation
	150	sparse vegetation
	160	closed to open forest regulary flooded

3 Fortran modules

Data Set (Total number of Classes)	Number of Class	Name of Class
	170	closed forest or shrubland permanently flooded
	180	closed to open grassland regularly flooded
	190	artificial surfaces
	200	bare areas
	210	water bodies
	220	permanent snow and ice
	230	undefined
<hr/>		
GLC2000 (23)		
	01	evergreen broadleaf tree
	02	deciduous broadleaf tree closed
	03	deciduous broadleaf tree open
	04	evergreen needleleaf tree
	05	deciduous needleleaf tree
	06	mixed leaf tree
	07	fresh water flooded tree
	08	saline water flooded tree
	09	mosaic tree / other natural vegetation
	10	burnt tree cover
	11	evergreen shrubs closed-open
	12	deciduous shrubs closed-open
	13	herbaceous cover closed-open
	14	sparse herbaceous or grass
	15	flooded shrub or herbaceous
	16	cultivated and managed areas
	17	mosaic crop/tree/natural vegetation
	18	mosaic crop/shrub or grass
	19	bare areas
	20	water bodies
	21	snow and ice
	22	artificial surfaces
	23	undefined
<hr/>		
GLCC (24)		
	01	urban and built-up land
	02	dryland cropland and pasture
	03	irrigated cropland and pasture
	04	mixed dryland/irrigated
	05	cropland/grassland mosaic
	06	cropland/woodland mosaic
	07	grassland
	08	shrubland
	09	mixed shrubland/grassland
	10	savanna
	11	deciduous broadleaf forest
	12	deciduous needleleaf forest
	13	evergreen broadleaf forest
	14	evergreen needleleaf forest
	15	mixed forest
	16	water bodies
	17	herbaceous wetland
	18	wooded wetland
	19	barren or sparsely vegetated
	20	herbaceous tundra
	21	wooded tundra

Data Set (Total number of Classes)	Number of Class	Name of Class
	22	mixed tundra
	23	bare ground tundra
	24	snow or ice
Ecoclimap 2 (218)		types not shown here

Table 4: Land-use classes for the different raw data sets.

After the allocation of the data a check is performed to query, if the user desires a domain that goes beyond the southern bound of the raw data. If it is the case, the GLCC target fields are allocated as well.

In case that Globcover is used, the grid for the single tiles must be defined as well.

Aggregation of the raw land-use data to the target field.

The definition and allocation part is done and the most important part, the aggregation of the raw data to the target grid can be performed. In order to be able to aggregate the data, the lookup table must first be initialized. The initial values differ for the various settings listed in table 5. Also the name of the lookup table must be defined using the integer numbers specified in the namelist 'INPUT_LU'. The integer number are listed together with their associated lookup table names in table 5.

Raw Data	Integer	Setting	Name of the lookup table
GLOBCOVER	1	operational settings	Asensio, 2011
	2	experimental settings, analog to lookup tables of ECOCLIMAP	Asensio, 2010
GLC2000	1	operational settings of GME	Ritter, 2007
	2	operational settings of COSMO	Heise, 2005
	3	experimental settings, analog to lookup tables of ECOCLIMAP	Asensio, 2010
GLCC	1	operational settings of GME	Ritter, 2007
	2	operational settings of COSMO	Heise, 2005
	3	experimental settings, analog to lookup tables of ECOCLIMAP	Asensio, 2010
Ecoclimap	n.a.	Ecoclimap lookup table	ecoclimap_lookup.TAB
ESA CCI-LC	1	experimental settings	Helmert, 2019

Table 5: Names of the lookup tables and the different possible settings for each raw land-use data set.

The following paragraphs describe computations on the raw data grid.

For GLC2000 and GLCC, the raw data is read in lines of a complete longitude going from 180 degrees east to 180 degrees west, through a loop over the latitude. Before any calculation is performed, it is tested if the value of the latitude is contained inside the targeted domain. In case it is not, the loop is cycled. Reading of the data line-wise can be done from the NetCDF file directly.

Using the routine *find_nearest_target_grid_element* each raw data pixel is assigned to a target grid point. A more precise description and a figure that describes the procedure can be found in paragraph 'Aggregation of the raw topography to the target grid' and in Fig. 5 in section 3.1.

As Globcover and ESA CCI-LC are composed of six tiles, the reading of the raw data must be performed in a different way than for the other three data sets. The reading of the data for Globcover is done in the same way as for the topography. Compare the paragraph 'Aggregation of the raw topog-

raphy to the target grid' in section 3.1. (As there is no need to calculate gradients for the land use, the corresponding variable, which contains three lines of raw data, is not used.)

The lookup table is then fed with the land use class, which gives a value for all the target fields listed in table 6.

Variable long name	Variable short name	Remark
Fraction Land	FR_LAND	
Ice fraction	FR_ICE	
Plant cover maximum	PLCOV_MX	
Plant cover minimum	PLCOV_MN	
Leaf area index maximum	LAI_MX	
Leaf area index minimum	LAI_MN	
Minimal stomata resistance	RS_MIN	
Urban area fraction	URBAN	
Fraction of deciduous forest	FOR_D	
Fraction of evergreen forest	FOR_E	
Longwave surface emissivity	EMISS_RAD	
Root depth	ROOTDP	
Roughness length	Z0	
Monthly leaf area index	LAI12	only Ecoclimap
Monthly plant cover	PLCOV12	only Ecoclimap
Monthly roughness length	Z012	only Ecoclimap

Table 6: The variables that are computed using the raw land-use data.

The number of grid points that fall into the same target grid and land use class are summed up. The values of the target fields are weighted with the whole pixel area and summed up. Except for the emissivity, which is the only land-use parameter that also has valid values over water, only land pixels are considered. Values that depend on the plant cover, such as PLCOV_MX, PLCOV_MN, LAI_MN, LAI_MX, RS_MIN, FOR_E, FOR_D, ROOTDP and z0, are weighted **with the plant cover maximum** in addition to the pixel area.

The following paragraphs describe computations on the target grid.

The total area and the land area of each target grid point is first defined. Then the weighted sums of the target fields derived in the previous step are normalized to obtain the definite values. The emissivity and the number of land use classes are normalized by the total area to obtain the correct emissivity and area fraction of each land use class. The other parameters are only considered if the area_land is larger than zero: FR_LAND and FR_ICE are normalized with the total area, URBAN, FOR_D, FOR_E, PLCOV_MN and PLCOV_MX are normalized by the land area, the ROOTDP, LAI_MN, LAI_MX and RS_MIN are normalized by the area covered by plants. If only sea pixels are found, all the fields are undefined.

Finally land-use classes are defined for target grid points that do not contain any raw data pixel. In contrary to the topography, where a bilinear interpolation is performed, here the nearest neighbor is searched. The associated land use class is used with the lookup tables, and the target fields are defined.

The target fields are written to a NetCDF buffer file, which can later be used for the consistency check. There is a file for the chosen land use data set, and one, if needed at all, for the GLCC land use data. Finally the allocated memory is deallocated again.

3.3.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid.org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_LU

- data input: GLC2000_byte.nc, GLCC_usgs_class_byte.nc, ECOCLIMAP_byte.nc, CORINE_globcover.nc, GLOBCOVER_0_16bit.nc - GLOBCOVER_5_16bit.nc, ECCI_300m_0.nc - ECCI_300m_5.nc
- Output: buffer file with landuse data (/lu_io_extpar/ lu_buffer_file) and buffer file with GLCC data (/glcc_io_extpar/ glcc_buffer_file)

3.4 *extpar_aot_to_buffer*

3.4.1 Short description of the subprogram *extpar_aot_to_buffer*

The executable *extpar_aot_to_buffer* aggregates aerosol optical thickness data to the target grid.

Target grid definition

The definition of the target grid is again done using the namelist 'INPUT_grid_org'. As the subroutines are exactly the same as the ones used in *extpar_topo_to_buffer*, it is referred to the subsection 'Target grid definition' in section 3.1, where the procedure is explained in more detail.

Raw aerosol optical depth data

The namelist 'INPUT_AOT' is kept very simple. It contains only the path and the name of the raw aerosol optical depth data. The integer switch (*iaot_type*) informs *extpar* which of the 4 available datasets has been chosen: 1 (Tegen), 2 (AeroCom), 3 (MACC-II), 4 (MACv2) or 5 (CAM5). Additionally, also the filenames of the buffer and output files for the aggregated data is specified.

In order to allocate the variables used to read the raw data, the dimensions of the raw data is defined. These dimensions include the number of rows and columns of the NetCDF raw data file, the number of months, which is equal to 12, as a full yearly cycle is described, and the number of types of aerosols contained in the raw data file. This number is 5 for *iaot_type*=1,2 or 3, as the raw data file contains the aerosol optical thickness information of black carbon, dust, organic matter, sulfate and sea salt. *iaot_type*=4 is used for a new formulation of the radiation-aerosol interaction available only in version of COSMO later than 5.04. This provides data of the aerosol optical thickness, the single scattering albedo and the asymmetry factor for the 8 spectral bands defined in the RG92 radiation scheme. *iaot_type*=5 is used only for ICON model. The raw data file contains the layer-integrated mass information of 11 types of aerosols: Sea Salt (3 bin), Mineral Dust (3 bin), hydrophilic and hydrophobic organic matter, hydrophilic and hydrophobic black carbon and sulfate. Also the raw data file contains the pressure for 60 vertical levels. The 3 first data-sets which provide raw data for different aerosol types refer to Tegen¹, AeroCom² and MACC-II³ whereas the fourth data-set is derived from MACv2⁴ and the fifth data-set is derived from CAM5⁵.

¹Tegen, I., P. Hollrigl, M. Chin, I. Fung, D. Jacob, and J. Penner 1997. Contribution of different aerosol species to the global aerosol extinction optical thickness: Estimates from model results. *J. Geophys. Res.*, 102, 23895-23915. http://pubs.giss.nasa.gov/abstracts/1997/Tegen_etal.html

²Kinne, S., M. Schulz, C. Textor, S. Guibert, Y. Balkanski, S.E. Bauer, T. Berntsen, T.F. Berglen, O. Boucher, M. Chin, W. Collins, F. Dentener, T. Diehl, R. Easter, J. Feichter, D. Fillmore, S. Ghan, P. Ginoux, S. Gong, A. Grini, J. Hendricks, M. Herzog, L. Horowitz, I. Isaksen, T. Iversen, A. Kirkevg, S. Kloster, D. Koch, J.E. Kristjansson, M. Krol, A. Lauer, J.F. Lamarque, G. Lesins, X. Liu, U. Lohmann, V. Montanaro, G. Myhre, J. Penner, G. Pitari, S. Reddy, . Seland, P. Stier, T. Takemura, and X. Tie: An AeroCom initial assessment optical properties in aerosol component modules of global models, *Atmos. Chem. Phys.*, 6, 1815-1834, 2006. <http://aerocom.met.no/aerocomhome.html>

³Morcrette, J.-J., O. Boucher, L. Jones, D. Salmond, P. Bechtold, A. Beljaars, A. Benedetti, A. Bonet, J. W. Kaiser, M. Razinger, M. Schulz, S. Serrar, A. J. Simmons, M. Sofiev, M. Suttie, A. M. Tompkins, and A. Untch, 2009: Aerosol analysis and forecast in the ECMWF Integrated Forecast System. Part I: Forward modelling, *J. Geophys. Res.*, 114D, D06206, doi:10.1029/2008JD011235 <http://www.gmes-atmosphere.eu/>

⁴Kinne, S., D. O'Donnel, P. Stier, S. Kloster, K. Zhang, H. Schmidt, S. Rast, M. Giorgetta, T. F. Eck, and B. Stevens (2013), MACv1: A new global aerosol climatology for climate studies, *J. Adv. Model. Earth Syst.*, 5, 704740, doi:10.1002/jame.20035.

⁵Bozzo, A., Benedetti, A., Flemming, J., Kipling, Z., Rmy, S. (2020). An aerosol climatology for global models based on the tropospheric aerosol scheme in the Integrated Forecasting System of ECMWF. *Geoscientific Model Development*, 13(3), 1007-1034.

Raw data set	resolution
Tegen	4 x 5 degree
AeroCom	1 x 1 degree
MACC-II	1.125 x 1.125 degree
MACv2	1 x 1 degree
CAMS	3 x 3 degree x 60 levels

Table 7: resolution of raw data-sets for aerosol optical depths.

In a next step, the complete raw data is read into memory; this is possible since the aerosol optical depth raw data is of rather coarse resolution (see table 7). Also, the grid of the raw data is determined from NetCDF meta data. Before the aggregation to the target grid can start, the target grid fields must be allocated, using the target grid, the number of months and aerosol types or spectral bands.

Aggregation of the aerosol optical depth to the target field

As the resolution of all raw data sets is so coarse, there is no need to go through the whole raw data set and find the corresponding target grid element. Here there is only one loop over the target grid. For every target grid element four surrounding raw data points are searched for. With these four points, a weight for the bilinear interpolation is computed. As the raw data grids of the 5 different aerosols are equal, the four surrounding points are the same for all months and aerosol types. Four new arrays (SW, SE, NE, NW) are then defined, which contain the four neighbor values, for each month and each type. These can now be used, together with the previously calculated weights, to calculate the bilinear interpolation.

Finally the data is saved in a NetCDF buffer and an output file, and the allocated variables are deallocated.

3.4.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid.org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_AOT
- data input: aot_GACP.nc, aod_AeroCom1.nc, aod_MACC_2003-2012.nc, aod_MACC_2003-2012_proc.nc, aot_MACv2.nc, aot_CAMS_2003-2013.nc
- Output: buffer file with aerosol data (/aerosol_io_extpar/ aot_buffer_file)

3.5 extpar_soil_to_buffer

3.5.1 Short description of the subprogram *extpar_soil_to_buffer*

The executable *extpar_soil_to_buffer* aggregates soil data of the FAO Digital Soil Map of the World or of the Harmonized World Soil Data (HWSD) to the target grid.

Target grid definition

The definition of the target grid is again done using the namelist 'INPUT_grid.org'. As the subroutines are exactly the same as the ones used in *extpar_topo_to_buffer*, it is referred to the subsection 'Target grid definition' in section 3.1, where the procedure is explained in more detail.

Raw soil data

The variables for the raw soil data are read from the namelist 'INPUT_SOIL'. These variables are the path and the names of the raw data files and two switches to decide whether the FAO or the HWSD data should be used and if the deep soil data is desired or not. The integer switch *isoil_data* determines the raw data and processing used: 1 for FAO, 2 for the HWSD data-set⁶ and 3 for the use of HWSD data with mapping to TERRA soil types. The switch to choose the production of deep soil information is a logical (only applicable to *isoil_data*=2). Additionally, the names of the buffer files are specified. Be aware that a change of the integer switch from FAO to HWSD requires also the manual replacement of the raw data file names in the namelist.

After reading the namelist, a check is made on the production of subsoil characteristics. This is only supported for HWSD data, and a warning is issued in case of bad usage.

The dimensions of the raw soil data are defined, which include the number of grid points in the latitudinal and longitudinal direction, as well as the number of soil data code of the raw data. These values are needed to allocate the soil data with the proper size.

The mapping between raw data sets specific codes and some standard soil types is defined; this concerns the soil types 'undefined', 'default', 'ice' and 'water'.

As the soil data is provided in one single file, all data can be read in one shot. The data that are read from the NetCDF file are the texture and the slope of the soil data and the soil code. The aggregation of the data is done in a different way for the FAO and HWSD data, as these result in two completely different variables. Moreover, for HWSD data, to conserve memory, the topsoil data are allocated first and aggregated to the target grid, before the same is done for the subsoil.

Aggregation of the FAO and HWSD data with TERRA mapping to the target grid

The following paragraphs describe computations on the raw data grid.

The soil data is read using a loop over the latitude and the longitude. This results in a point-wise reading of the raw data. As soon as the point is read, its corresponding target grid element is defined. If the regular latitude/longitude grid point is not contained in the target grid, a new point is read. If however the point is inside the target grid, the aggregation can begin.

The number of raw data pixels is increased by one, if a raw data point can be assigned to a target grid point. This number is later used to define the fraction land defined by the soil data. The corresponding soil unit is deduced from the raw data. If the soil unit is zero, this is an ocean pixel and the number of sea points is increased by one. If the soil code differs from zero, the number of land points is increased by one. The soil code is then associated to either a special or a normal soiltype. For all the special soiltypes such as ice, rock, salt, histosols, dunes and no data flags the respective texture (coarse, medium, fine) are defined using a lookup table. All other soil units are described using the texture available in the raw data. These values define the final texture variable 'texture'.

The following paragraphs describe computations on the target grid.

In the following a loop is opened over the target grid points. First of all the fraction land is defined using the number of land pixels minus the number of inland water pixels, which is then averaged by the number of raw data pixels that were available for the target grid element. In a next step the texture for every target grid element is defined. For the special soiltypes (texture larger than 900) the corresponding number is associated. For the normal soiltypes (texture smaller than 900) the texture is calculated as average of the summed up texture. The resulting texture value is multiplied by 100 and converted into an integer number. This number is used to associate the final soiltype to every target grid element. The soiltypes are described in more detail in table 8. For target grid points that do not contain any raw data points, the nearest neighbor in the raw data is defined. If the target grid point is outside the raw data grid the slope is defined as zero and the texture as undefined.

⁶Release 5.0 of COSMO and 2.0 of INT2LM do not support HWSD data, as the representation of the soil associated with this new data set has changed and is based on the use of pedotransfer functions and on fraction of soil components (e.g. clay, silt, ...)

TERRA Code	Soiltype	raw data code
1	ice and glacier	9001
2	rock, lithosols	9002
3	sand	9003 (salt), 9005 (shifting sands and dunes) and coarse texture
4	sandy loam	coarse to medium texture
5	loam (default soiltype)	9009 (undefined), 9012 (dominant part undefined), medium texture
6	loamy clay	medium to fine texture
7	clay	fine texture
8	histosols (peat)	9004
9	water	9000 (undefined: inland water), -9 (undefined: ocean)

Table 8: TERRA soiltypes and their respective FAO raw data codes.

Aggregation of the HWSD data to the target grid

The aggregation starts again with a loop over the latitudes and longitudes. For each grid point a target grid element is looked for. If there is a target grid element, the aggregation can start. The soiltype is defined using the raw data value, if it is above zero, and zero otherwise. Additionally, all the ocean, land and lake points are counted in order to determine the land fraction which is calculated as the difference between the summed up land and lake points normalized by the number of raw data pixels available. For target grid points with no raw data, the nearest neighbor in the raw data is defined.

The resulting soiltype is not yet usable, as it contains numbers coded in a world code and not in TERRA soiltypes. This transformation is done in the consistency check, where the special soiltypes of the HWSD data, specified in table 9, are packed in the variable 'SOILTYP' the normal soiltypes are given in fractions of sand, silt, clay and organic carbon, and the bulk density is also given.

TERRA Code	Soiltype	TERRA Code	Soiltype
1	ice and glacier	8	histosols (peat)
2	rock, lithosols	9	water
3	sand	10	alkali flat
4	sandy loam	11	shifting sand, dunes
5	loam (default soiltype)	12	Urban, human disturbed
6	loamy clay	225	Unknown
7	clay		

Table 9: New TERRA soiltypes deduced from the HWSD data.

Output of the soil data

The soiltypes and the fraction land, together with the undefined value, the latitudes and longitudes are saved in a NetCDF buffer file. This is later used to perform the consistency check, which is especially important for the HWSD data, as the main transformation of the data takes place there.

3.5.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid.org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_SOIL

⁷Soiltypes written in bold indicate a special soiltype.

- data input: FAO_DSMW_double.nc, FAO_DSMW_float.nc, HWSD0_30_topsoil.nc, HWSD30_100_subsoil.nc
- Lookup tables for HWSD: LU_TAB_HWSD_UF.data, HWSD_DATA_COSMO.data, HWSD_DATA_COSMO_S.data
- Output: buffer file with soil data (/soil_io_extpar/ soil_buffer_file)

3.6 *extpar_flake_to_buffer*

3.6.1 Short description of the subprogram *extpar_flake_to_buffer*

The executable *extpar_flake_to_buffer* aggregates lake depth data and lake fraction to the target grid.

Target grid definition

The definition of the target grid is again done using the namelist 'INPUT_grid.org'. As the subroutines are exactly the same as the ones used in *extpar_topo_to_buffer*, it is referred to the subsection 'Target grid definition' in section 3.1, where the procedure is explained in more detail.

Raw lake data

As only the target grid dimensions are needed to allocate the target fields, this is done right after the definition of the target grid. Then the namelist 'INPUT_FLAKE' is read to define the path and the filename of the raw lake data. Also the names of the buffer and the output file for the consistency check are given. Once more the dimensions of the raw data are needed to allocate the raw data correctly; these dimensions are deduced from the netcdf file directly and the raw data grid is defined.

Aggregation of the lake data to the target grid

The following paragraphs describe computations on the raw data grid.

The data is read row-wise, through a loop over the latitudes, skipping all latitudes not inside the user specified domain. If a row is kept, a new loop over the longitudes is started to treat the raw data point-wise. For each point, the corresponding target field element is defined. This is done in the same way described in the subsection 'Aggregation of the topography to the target grid' in section 3.1 and Fig. 5. The number of raw data pixels that contribute to the target grid value are summed up as well as the lake depth, which is multiplied by a scale factor deduced from the area of each pixel that contributes to a lake fraction.

The following paragraphs describe computations on the raw data grid.

The lake fraction is derived and the lake depth is obtained by normalizing the weighted sum previously computed. Where no lake depth is available the value is set to undefined (-1). In case that no raw data pixel is available the nearest neighbor in the raw data is searched for.

The target fields are then written to a netcdf buffer and output file. Finally the allocated memory can be released.

3.6.2 Used namelist files and data in-/output:

- namelists files: INPUT_grid.org, INPUT_COSMO_GRID, INPUT_ICON_GRID, INPUT_FLAKE
- data input: GLDB_lakedepth.nc
- Output: buffer file with flake data (/flake_io_extpar/ flake_buffer_file)

3.7 extpar_consistency_check

3.7.1 Short description of the subprogram *extpar_consistency_check*

The *extpar_consistency_check* is performed after all raw data have been aggregated to the target grid to remove any inconsistencies that may appear among the different data and to derive additional information using multiple raw data sources.

Reading of namelists

Before the grid is defined, the namelists 'INPUT_RADTOPO', 'INPUT_ORO' and 'INPUT_SOIL' are read to obtain the settings of the different switches that are used (e.g. *lradtopo*, *itopo_type*, *lssso_param*, *isoil_data*, *ldeep_soil*). Then the namelist 'INPUT_grid_org' is read to obtain the target grid information and the grid type.

In a next step the 'INPUT_LU' is read by *extpar_consistency_check* to check if the GLCC data set is required, which is the case if the target grid domain reaches more to the south than the chosen raw land-use data set. (Globcover and GLC_2000 are not global.)

If the namelist INPUT_ERA is present (indicating that one uses the ERA climatologies generated by *extpar_era_to_buffer*) the buffer file name is retrieved. If this namelist is not present (legacy climatologies from ICON-REMAP-TOOL are used), the buffer file names in INPUT_CHECK are read. After that step, all other namelists of the Extpar modules are read in order to retrieve the buffer file name for each data set. These files are read and all the variables needed for the final external parameters file are allocated.

An additional namelist that is used is 'INPUT_CHECK', it contains a couple of switches to define the processing in the consistency check.

The first task after reading the namelists is to derive the correct land sea mask from the land use data. If the GLCC data must be used, the land sea mask below the southern band is deduced from GLCC.

Then the total roughness length is computed as the sum of the roughness length deduced from the land-use and the topography.

Consistency check for water and ice pixels

The definition of a water grid element is based on the land-use data. The vegetation is set to zero for all water grid elements and FAO derived soil type is set to water. For non water pixels with undefined or invalid soil type, the FAO derived soil type is either set to default, which is loam, or to ice for regions that are below 60 degrees south (where only Antarctica is located).

All the points that are classified as ice in the land-use data but not in the FAO derived soil type, are changed to ice in the latter; the vegetation of these pixels is set to zero.

The HWSO derived soiltype needs a transformation from the world code to the TERRA code, which is performed here. The world code is decoded with the TERRA HWSO lookup table, to define the regions that contain a special soiltype (see the special soiltypes in table 9). For each grid point the world code is associated to the single fractions of the soil composition, using an other lookup table. If there is a point that does not contain a bulk density it is calculated using the formula of the cultivated topsoil or the compact subsoil from Hollisa et al. (2012)⁸ and Woesten et al. (1999)⁹. Furthermore there is a special treatment of peat with histosols. The whole procedure is also done for the subsoil, if it is desired at all.

⁸J.M. Hollisa, J. Hannamb and P.H. Bellamy, February 2012, Empirically-derived pedotransfer functions for predicting bulk density in European soils, European Journal of Soil Science, 63, 96109 doi: 10.1111/j.1365-2389.2011.01412.x

⁹J.H.M. Woesten, A. Lilly, A. Nemes and C. Le Bas, Development and use of a database of hydraulic properties of European soils, Geoderma, Volume 90, Issues 34, July 1999, Pages 169-185, doi: 10.1016/S0016-7061(98)00132-3.

Consistency check of lake data

Water grid points are either declared as lake or ocean, thus over land a fraction lake and over the ocean a fraction ocean is defined. Where the fraction land deduced from the topography is smaller than 0.99 the fraction ocean is defined. All the other points are used to determine the fraction lake. Both fractions are defined such that `fr_lake` or `fr_ocean` plus `fr_land_lu` (fraction land deduced from land-use) sum up to one. Some smaller seas must be defined manually, thus for the region of the Dead Sea and the Caspian Sea not fraction lake but fraction ocean is calculated.

For `fr_land`¹⁰ and `fr_ocean`¹¹ larger than a half, the lake depth is set to undefined. A default value for the lake depth is used for grid elements with a lake fraction¹² larger than a half and a negative lake depth. Additionally a maximum and minimum lake depth is defined. Included is also a manual correction of the depth of Lake Constance.

Consistency check of albedo data

The consistency check of the albedo data concerns land pixels that have a albedo smaller than 0.07. For these pixels a weighted bilinear interpolation is performed. Only land points are used for the interpolation, if there is no surrounding land point a warning message is printed. Values that are still too small receive a soiltype dependent albedo. This is done for all three wavelengths.

Consistency check of NDVI data

The next consistency check is performed with the normalized difference vegetation index (NDVI). The NDVI values are set to undefined for water grid points. Additionally, values that are smaller than a predefined value are set to exactly this value.

Consistency check of the temperature climatology

The consistency check of the temperature climatology contains a height correction and is only performed for the finer resolved temperature climatology (e.g. `it_cl.type = 1`). The temperature is set to undefined for all the sea points. For land points that have a valid temperature, it is adjusted to the height. This is done by considering a constant temperature rate of 0.65 K per 100m ($\frac{dT}{dh} = -\frac{0.65K}{100m}$).

Target points that do not contain temperature values larger than zero are filled with surrounding values. First a valid point is looked for in the surrounding 3×3 grid box. If still no valid point can be found, it is searched along the longitude, and if nothing else helps the nearest neighbor is tried.

Consistency check of all other fields

All other fields are assumed to be independent and are written to the output file exactly as they were read in. A special treatment applies to the ISA, AHF, EMISS and S_ORO fields. Whenever their respective namelist input file is missing in the working directory where `extpar_consistency_check` is executed these fields are not added to the output file.

Definition of special points

Be aware that the definition of special points has only been tested for the COSMO grid and can only be used if the FAO raw soil type is used. At the moment there are three special points (1: Falkenberg, 2: Waldstation, 3: Lindenberg). At each of these points, values for `soiltype_sp`, `z0_sp`, `rootdp_sp`, `plcovmn_sp`, `plcovmx_sp`, `laimn_sp`, `laimx_sp` can be explicitly set by the user. The coordinates of the special point are also user specified. If no special treatment at these points is desired the `number_special_points` must be set to zero (see table 10). If no special treatment is desired at all, the integer switch `i_lsm_treatment` can be set to 1 instead of 2.

¹⁰derived from the land use data

¹¹derived from the land use data

¹²derived from the lake data set

number_special_points	Treatment of special points
0	NO treatment of special points
1	special treatment of Falkenberg
2	special treatment of Falkenberg and Waldstation
3	special treatment of Falkenberg, Waldstation and Lindenberg

Table 10: Usage of the namelist parameter `number_special_points`.

Reduced main memory usage

Since Exptar Version 5.4 a new feature was introduced which allows the running of `extpar_consistency_check` for very high resolution global grids without any restrictions on the hardware memory specifications. A POSIX mmap based implementation of disk caching arrays is used to use main memory as much as possible and, if more memory is required, the duty to handle this request is delegated to the kernel. A requirement to run this properly is the provision of swap space in the expected total memory use. With this technique we could process a global R2B11 ICON grid (around 1.25 km grid resolution) on a server with 256 GB main memory. Of course processing gets quite slow, but is still in the order of a couple of cups of coffee.

The feature can be enabled with the namelist variable

`l_use_array_cache = .TRUE.` in namelist `extpar_consistency_check_io`. The namelist variable default is `l_use_array_cache = .FALSE.`, which is selecting the standard heap allocation by Fortran's `ALLOCATE` statement.

Writing output

The final results are written into a netcdf file. The output file name can be specified in the namelist 'INPUT_CHECK'.

Since Exptar Version 5.4 the output possibilities have been extended for ICON only. The Extpar output procedure for COSMO did not change with Version 5.4. As ICON and a lot of its associated tools (eg. CDO, DWD icontools) are already using a single abstract interfacing library CDI, a re-implementation for the final Extpar output procedure with CDI to prepare for future developments is provided. Note, that this re-implementation replaces the former writing-routine completely. For a detailed description of CDI look at

<https://code.mpimet.mpg.de/projects/cdi>.

Used namelist files and data in-/output

- namelists files: `INPUT_grid.org`, `INPUT_COSMO_GRID`, `INPUT_ICON_GRID`, `INPUT_CHECK`, `INPUT_*`
- data input: all buffer files from the Extpar modules defined in the 'INPUT_*' namelist files
- data output: netCDF containing all external parameters (`/extpar_consistency_check_io/ netcdf_output_filename`)

4 Python modules

4.1 General workflow

The general workflow of all Python modules is the same. An exemplary workflow of the Python modules is described below:

At the beginning of the program information about the environment on which Extpar is running is written to the logfile and all left-overs from prior executions of the same Extpar module are deleted. In a next step each parameter from the namelist 'namelist.py' is checked for correctness as well as assigned to an internal variable for later use in the program. The specification about the target grid is directly read from the Fortran namelist-files 'INPUT_grid.org'. The next step in the modules involves the generation of all necessary meta-data for the buffer files and the write of a namelist files in the style of a Fortran namelist, containing all information needed for the consistency_check at the end. In case of a COSMO target grid, a grid specification file is written, that is later used by CDO for the interpolation.

After this is all setup, the most compute-intensive parts like the remapping to the target grid or data modifications are done using CDO. The Python program launches a subshell executing the CDO in it. The output from CDO is reshaped in order to fit the dimensions of the buffer files. After the reshape, the fields and its corresponding metadata is written to a netCDF buffer file. The last step of the programme again deletes all intermediate netCDF or other files written during runtime, that do not serve any purpose.

Module-specific modifications or additional computations are described in the paragraph *Data processing* of each Python module.

Namelist

The namelist 'namelist.py' contains the Python dictionaries 'input_alb', 'input_tclim', 'input_emiss', 'input_ndvi', 'input_ahf' and 'input_isa'. These dictionaries replace their corresponding Fortran namelist files 'INPUT_*'.

'input_alb' provides information about the albedo data type and the paths and filenames of the input/output data.

'input_tclim' contains a switch to determine the type of data (coarse or fine) as well as the paths and filenames of the input/output data.

'input_emiss' contains a switch to determine the type of emissivity data (full range or long-wave) and the filename and paths of the input/output data.

'input_ndvi' only provides information about the the path and the filenames of the input/output data.

'input_era' only provides information about the the path and the filenames of the input/output data.

'input_isa' contains a switch determine the type of ISA data and provides information about the the path and the filenames of the input/output data.

'input_ahf' contains a switch determine the type of AHF data and provides information about the the path and the filenames of the input/output data.

4.2 extpar_alb_to_buffer

4.2.1 Short description of the subprogram *extpar_alb_to_buffer*

The executable *extpar_alb_to_buffer* allows the aggregation of two different kinds of albedo data to the target grid. The first kind is a climatology of monthly values of total albedo derived from MODIS satellite data for the 3 spectral bands visible, near infrared and ultraviolet. The second kind contains information for soil albedo only in dry and saturated conditions. It originates from the Community Land Model¹³.

¹³https://svn-ccsm-inputdata.cgd.ucar.edu/trunk/inputdata/Ind/clm2/rawdata/mksrf_soilcol.081008.nc

Lawrence, P. J. and T. N. Chase (2007). "Representing a new MODIS consistent land surface in the Community Land Model (CLM 3.0)." *Journal of Geophysical Research-Biogeosciences* 112(G1).

Table 3.3 in: Oleson, K.W., D.M. Lawrence, G.B. Bonan, M.G. Flanner, E. Kluzek, P.J. Lawrence, S. Levis, S.C. Swenson, P.E. Thornton, A. Dai, M. Decker, R. Dickinson, J. Feddema, C.L. Heald, F. Hoffman, J.-F. Lamarque, N. Mahowald, G.-Y. Niu, T. Qian, J. Randerson, S. Running, K. Sakaguchi, A. Slater, R. Stockli, A. Wang, Z.-L. Yang, Xi. Zeng, and Xu. Zeng, 2010:

Data processing

The data is remapped to the target grid using the *distance-weighted average* interpolation. CDO first generates the weights for the interpolation from one of the input files and then applies these weights to all input files. After the interpolation took place, all values in the range of -100000 - 0.02 are set to 0.02 to prevent unrealistic data-points. All other steps in `extpar_alb_to_buffer` are following the general workflow of the Python scrips.

4.2.2 Used namelist files and data in-/output

- namelist files: `namelist.py` (dict: `input_alb`), `INPUT_grid.org`, `INPUT_COSMO_GRID`, `INPUT_ICON_GRID`
- generate namelist: `INPUT_ALB`
- data input: `month_alb.nc`, `month_alnid.nc`, `month_aluvd.nc`, `global_soil_albedo.nc`
- data output: buffer file with albedo data (`input_alb: alb_buffer_file`)

4.3 extpar_cru_to_buffer

4.3.1 Short description of the subprogram `extpar_cru_to_buffer`

The executable `extpar_cru_to_buffer` aggregates the temperature climatology of the Climate Research Unit (CRU) to the target grid. The namelist '`namelist.py`' gives the information of the path and the name of the raw temperature climatology data file. Additionally, the filename for the buffer is provided. There is an integer switch (`it_cl_type`), which allows the choice between a newer higher resolved data set for land surfaces only (1) and an older coarser raw data set for sea surfaces in combination with the higher resolved data set over land (2). Aggregation of the coarse data set over land surfaces is no longer supported since Extpar Version 5.4.

Data processing

The data processing with CDO for `it_cl_type = 1` involves 4 steps:

1. Set seapoints in the data to missing value.
2. Extract the fields 'HSURF' from the fine data set.
3. Merge the fields from step 1 and step 2.
4. Remap data from step 3 to the target grid using *distance-weighted average* interpolation.

The data processing with CDO for `it_cl_type = 2` involves 5 steps:

1. Convert coarse data from Celsius to Kelvin, calculate yearly mean values and remap coarse data to the grid of the higher resolved data set.
2. Take landpoints from the fine data set and the seapoints from the data processed in step 1.
3. Extract surface height from the buffer file of `extpar_topo_to_buffer`
4. Smooth data processed in step 2 and remap to target grid using *distance-weighted average* interpolation.
5. Correct data processed in step 4 with the surface height extracted in step 3.

All subsequent processing on the data follows the general workflow of the Python scrips.

Technical Description of version 4.0 of the Community Land Model (CLM). NCAR Technical Note NCAR/TN-478+STR, National Center for Atmospheric Research, Boulder, CO, 257 pp.

4.3.2 Used namelist files and data in-/output:

- namelists files: `namelist.py` (dict: `input_tclim`), `INPUT_grid.org`, `INPUT_COSMO_GRID`, `INPUT_ICON_GRID`
- generate namelist: `INPUT_TCLIM`
- data input: `absolute_hadcrut3.nc`, `CRU_T2M_SURF_clim.nc`, `CRU_T_SOIL_clim.nc`, `orography_buffer_file` (`it_cl_type = 2` only)
- Output: buffer file with CRU data (`input_tclim: t_clim_buffer_file`)

4.4 *extpar_emiss_to_buffer***4.4.1 Short description of the subprogram *extpar_emiss_to_buffer***

The executable *extpar_emiss_to_buffer* aggregates CAMEL (Combined ASTER and MODIS Emissivity for Land) data to the target grid. For the aggregation of the emissivity the namelist 'namelist.py' provides the path and the file name of the input data. The buffer file name is defined as well. There exists the integer switch (`iemiss_type`) to determine whether one wants to use the broad band emissivity for the 3.6 and 14.3 micron spectral range (1) or the broad band emissivity between 8.0 and 13.5 micron spectral range (2).

Data processing

After the generation of the interpolation weights artificial low values below 0.5 are set to -999. In a subsequent processing step -999 is set to the value for missing data. In order to not have missing data in the field to interpolate, all missing values are set to the values of its nearest neighbour. The last step involves the *first order conservative* interpolation to the target grid. After the remapping with CDO two additional fields are computed:

- `EMISS_MAX`, the maximum `EMISS` value over 12 months
- `EMISS_MRAT`, the monthly ratio with respect to the maximum `EMISS`

4.4.2 Used namelist files and data in-/output:

- namelists files: `namelist.py` (dict: `input_emiss`) `INPUT_grid.org`, `INPUT_COSMO_GRID`, `INPUT_ICON_GRID`
- generate namelist: `INPUT_EMISS`
- data input: `CAM_bbe_full_2010-2015.nc` or `CAM_bbe_lw_2010-2015.nc`
- Output: buffer file with CAMEL data (`input_emiss: emiss_buffer_file`)

4.5 *extpar_ndvi_to_buffer***4.5.1 Short description of the subprogram *extpar_ndvi_to_buffer***

The executable *extpar_ndvi_to_buffer* aggregates NDVI data (Normalized Differential Vegetation Index) to the target grid. The namelist 'namelist.py' only contains the path and the file name of the raw NDVI data. No other parameters can be set.

For the aggregation of the normalized differential vegetation index the namelist 'namelist.py' is simple. It contains the path and the filename of the raw data set, as well as the names of the buffer. No other parameters can be set.

Data processing

The remapping to the target grid uses the *first order conservative* interpolation. After the remapping with CDO two additional fields are computed:

- NDVI_MAX, the maximum NDVI value over 12 months
- NDVI_MRAT, the monthly ratio with respect to the maximum NDVI

4.5.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_ndvi), INPUT_grid.org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_NDVI
- data input: NDVI.1998.2003.nc
- Output: buffer file with NDVI data (input_ndvi: ndvi_buffer_file)

4.6 extpar_era_to_buffer

4.6.1 Short description of the subprogram *extpar_era_to_buffer*

The executable *extpar_era_to_buffer* aggregates ERA data (T2M, SST, W_SNOW and ORO) to the target grid. It replaces the two NetCDF-Files generated by ICON-REMAP at DWD. Note that this executable is for Icon-grids only.

For the aggregation of the ERA climatologies the namelist 'namelist.py' is simple again. It contains the type of ERA climatology (ERA5 (1) or ERA-I (2)) the path and the filenames of the raw data sets, as well as the names of the buffer. No other parameters can be set.

Data processing

The remapping to the target grid uses the *first order conservative* interpolation. After the remapping with CDO the field W_SNOW is scaled by a factor 1000. No other processing steps take place.

4.6.2 Used namelist files and data in-/output:

- namelists files: namelist.py (dict: input_era), INPUT_grid.org, INPUT_COSMO_GRID, INPUT_ICON_GRID
- generate namelist: INPUT_ERA
- data input: ERA5_ORO.1990.nc, ERA5_SD.1990.2019.nc, ERA5_SST.1990.2019.nc and ERA5_T2M.1990.2019.nc
ERA-I_ORO.1986.nc, ERA-I_SD.1986.2015.nc, ERA-I_SST.1986.2015.nc and ERA-I_T2M.1986.2015
- Output: buffer file with ERA data (input_era: era_buffer_file)

4.7 extpar_isa_to_buffer

4.7.1 Short description of the subprogram *extpar_isa_to_buffer*

The executable *extpar_isa_to_buffer* allows the aggregation or interpolation of data on the fraction of impervious surface area needed by TERRA_URB to the target grid.

For the aggregation of the ISA the namelist 'namelist.py' is simple again. It contains the type of ISA (NOAA (1) or EEA (2)) the path and the filenames of the raw data sets, as well as the names of the buffer. No other parameters can be set. Note that the underlying processing does not differ between different types of ISA

The remapping to the target grid uses the *bilinear* interpolation. No other processing steps take place.

4.7.2 Used namelist files and data in-/output:

- namelists files: `namelist.py` (dict: `input_isa`), `INPUT_grid.org`, `INPUT_COSMO_GRID`, `INPUT_ICON_GRID`
- generate namelist: `INPUT_ISA`
- data input: `EEA_ISA_16bit_lonlat.nc` (`isa_type=2`), `NOAA_ISA_16bit_lonlat.nc` (`isa_type=1`)
- Output: buffer file with ISA data (`input_isa: isa_buffer_file`)

4.8 *extpar_ahf_to_buffer***4.8.1 Short description of the subprogram *extpar_ahf_to_buffer***

The executable *extpar_ahf_to_buffer* allows the aggregation or interpolation of data on the anthropogenic heat flux needed by `TERRA_URB` to the target grid.

For the aggregation of the AHF the namelist '`namelist.py`' is simple again. It contains the type of AHF (2.5min (1) or 30sec (2)) the path and the filenames of the raw data sets, as well as the names of the buffer. No other parameters can be set. Note that the underlying processing does not differ between different types of AHF

The remapping to the target grid uses the *bilinear* interpolation. No other processing steps take place.

4.8.2 Used namelist files and data in-/output:

- namelists files: `namelist.py` (dict: `input_ahf`), `INPUT_grid.org`, `INPUT_COSMO_GRID`, `INPUT_ICON_GRID`
- generate namelist: `INPUT_AHF`
- data input: `AHF_2006_2.5min_lonlat.nc` (`ahf_type=1`), `AHF_2006_NOAA_30sec_lonlat.nc` (`ahf_type=2`)
- Output: buffer file with AHF data (`input_ahf: ahf_buffer_file`)

5 Current limitations**5.1 General limitations**

The EXTPAR software is subject to several limitations:

- The ASTER domain can only be used from 60°N to 60°S. Be aware that an additional border of several gridpoints is needed if the topographically corrected parameters are desired. If the ASTER domain is exceeded a warning message is printed and the program *extpar_topo_to_buffer* is aborted.
- The ASTER data shows some deficits, which are listed below:
 - Beyond 60 degrees north and south, the ASTER raw data set features several areas where no value is available e.g., over Finland (private communication with HIRLAM).
 - Some bogus regions may appear in complex topography. One of these regions is located near Grindelwald in Switzerland.
 - The ASTER data are subject to artefacts of the satellite fly-over bands. Discontinuities can be spotted at the borders of such bands. In high latitudes these bands are better visible than in the low latitudes.
 - As the correction of these deficits are time consuming no effort has been expended to remove these.
 - The ASTER data might be subject to a shift of a half gridpoint (15 meters) in both directions.

5 Current limitations

- There is no 3 km filtered ASTER or MERIT/REMA data set to derive the subgrid scale orography (SSO) parameters and the roughness length (z_0) for ASTER.
- The HWSD raw data is in a test phase. Furthermore a new Version of Int2lm and TERRA is needed to make use of these data sets.
- The subsoil can only be used if the HWSD data is used for the topsoil. If the FAO and the HWSD data are combined a warning message is printed and the `ldeep_soil` parameter is set to `.FALSE`.
- The special points are only tested for the COSMO grid. Also it is not possible to use these corrections if the soil raw data set is HWSD.
- Array-caching in the `consistency_check` is only supported for GCC compiler.
- CAMS aerosol data `iaot_type = 5` is only support for Intel compiler.

6 Namelist Input for Extpar

Extpar uses 3 types of namelists in order to determine in which way data is processed.

- Fortran namelists (INPUT_*)
- Python dictionaries (input_* in namelist.py)
- Fortran namelists written by Python scripts

Whereas for the Fortran namelists and the Python dictionaries the user can specify parameters and filenames, the Fortran namelists generated during runtime by the Python scripts do not allow any user interaction.

6.1 Namelist files

Namelist file	Purpose	Made by script	Used by program
INPUT_grid.org	define target grid type	runscript	extpar_consistency_check extpar_aot_to_buffer extpar_landuse_to_buffer extpar_topo_to_buffer extpar_cru_to_buffer extpar_ndvi_to_buffer extpar_soil_to_buffer extpar_flake_to_buffer extpar_isa_to_buffer extpar_ahf_to_buffer extpar_emiss_to_buffer
INPUT_COSMO_GRID	define target domain for COSMO grid	runscript	extpar_consistency_check extpar_aot_to_buffer extpar_landuse_to_buffer extpar_topo_to_buffer extpar_cru_to_buffer extpar_ndvi_to_buffer extpar_soil_to_buffer extpar_flake_to_buffer extpar_isa_to_buffer extpar_ahf_to_buffer extpar_emiss_to_buffer
INPUT_ICON_GRID	define target domain for ICON grid	runscript	extpar_consistency_check extpar_aot_to_buffer extpar_landuse_to_buffer extpar_topo_to_buffer extpar_cru_to_buffer extpar_ndvi_to_buffer extpar_soil_to_buffer extpar_flake_to_buffer extpar_isa_to_buffer extpar_ahf_to_buffer extpar_emiss_to_buffer
INPUT_ORO	settings for orography data	runscript	extpar_topo_to_buffer
INPUT_OROSMOOTH	settings for orography smoothing	runscript	extpar_topo_to_buffer

Namelist file	Purpose	Made by script	Used by program
INPUT_RADTOPO	settings for generating topographical shading fields	runscript	extpar_topo_to_buffer
INPUT_SCALE_SEP	settings to control scale separation for SSO an Z0 calculation	runscript	extpar_topo_to_buffer
INPUT_LU	settings for landuse data	runscript	extpar_landuse_to_buffer
INPUT_AOT	settings for aerosol data	runscript	extpar_aot_to_buffer
INPUT_TCLIM	settings for temperature data	extpar_cru_-to_buffer	extpar_consistency_check
INPUT_NDVI	settings for NDVI data	extpar_ndvi_-to_buffer	extpar_consistency_check
INPUT_SOIL	settings for soil data	runscript	extpar_soil_to_buffer
INPUT_FLAKE	settings for lake data	runscript	extpar_flake_to_buffer
INPUT_ALB	settings for albedo data	extpar_albedo_-to_buffer	extpar_consistency_check
INPUT_ISA	settings for fraction of impervious surface area data	extpar_isa_to_buffer	extpar_consistency_check
INPUT_AHF	settings for anthropogenic heat flux data	extpar_ahf_to_buffer	extpar_consistency_check
INPUT_EMISS	settings for emissivity data	extpar_emiss_-to_buffer	extpar_consistency_check
INPUT_ERA	settings for ERA data	extpar_era_-to_buffer	extpar_consistency_check
INPUT_CHECK	settings for the consistency check	runscript	extpar_consistency_check

6.2 Grid definition

The specification of the model type (COSMO or ICON) is done in the namelist file `INPUT_grid.org`, the detailed target grid description for the model domain has to be provided in the namelists files `INPUT_COSMO_GRID` or `INPUT_ICON_GRID`.

6.2.1 general

NAMELIST /grid_def/ (INPUT_grid.org)

The namelist `/grid_def/` defines the target grid type and the filenames with the namelists of the detailed target grid definition.

Parameter	Type	Default	Unit	Description
<code>igrd_type</code>	integer			target grid type, 1 for ICON, 2 for COSMO
<code>domain_def_namelist</code>	character			namelist file with domain definition
<code>domain_refinement</code>	character			namelist file with domain refinement definition (e.g. for the ICON grid)

6.2.2 Icon

NAMELIST /icon_grid_info/ (INPUT_ICON_GRID)

The namelist `/icon_grid_info/` specifies the filenames and the directory of the Icon grid files with the coordinates of the Icon grid.

Parameter	Type	Default	Unit	Description
<code>icon_grid_dir</code>	character			path to directory which contains the ICON grid file with the coordinates

Parameter	Type	Default	Unit	Description
icon_grid_nc_file	character (max_dom)			filename of the ICON grid file with the coordinates

6.2.3 COSMO

NAMELIST /Imgrid/ (INPUT_COSMO_GRID)

The COSMO grid is defined by a rotated latlon-grid.

Parameter	Type	Default	Unit	Description
pollon	real	-170.	deg	longitude of the rotated north pole (in degrees, $E > 0$)
pollat	real	32.5	deg	latitude of the rotated north pole (in degrees, $N > 0$)
polgam	real	0.	deg	longitude (in the rotated system) of the geographical north pole
dlon	real	0.08	deg	grid point distance in zonal direction (in degrees)
dlat	real	0.08	deg	grid point distance in meridional direction (in degrees)
startlon_tot	real	-1.252	deg	transformed longitude of the lower left grid point of the total domain (in degrees, $E > 0$)
startlat_tot	real	-7.972	deg	transformed latitude of the lower left grid point of the total domain (in degrees, $N > 0$)
ie_tot	integer	51		number of grid points in zonal direction
je_tot	integer	51		number of grid points in meridional direction
ke_tot	integer	0		number of grid points in vertical direction

6.3 Orography

NAMELIST /oro_runcontrol/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
lcompute_sgs1	logical	.false.		switch to activate subgrid-slope calculation

NAMELIST /orography_raw_data/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
itopo_type	integer			switch to choose an orography raw data set; 1 GLOBE, 2 ASTER, 3 MERIT/REMA
lso_param	logical			switch to choose if SSO parameters should be generated or not
raw_data_orography_path	character			path to orography raw data

6 Namelist Input for Extpar

Parameter	Type	Default	Unit	Description
nfiles_column	integer	GLOBE: 4 ASTER, MER- IT/REMA: x		number of tile columns of desired region
nfiles_row	integer	GLOBE: 4 ASTER, MER- IT/REMA: x		number of tile rows of desired region
topo_files	character			filenames of GLOBE (16 tiles) / ASTER (240 tiles)/ MERIT/REMA (72 tiles) raw data sets
lsubtract_mean_slope	logical	.FALSE. for op- erational NWP- ICON		treatment of mean slope in computation of SSO parameters for ICON

NAMELIST /orography_io_extpar/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
orography_buffer_file	character			name for orography buffer file
orography_output_file	character			name for orography output file

NAMELIST /sgsl_io_extpar/ (INPUT_ORO)

Parameter	Type	Default	Unit	Description
lpreproc_oro	logical	.false.		read S_ORO from existing NetCDF (.false.) or preprocess from raw topography datasets (.true.)
sgsl_files	character			filenames of raw data tiles to be used S_ORO_A10 to S_ORO_P10 (GLOBE) or S_ORO_T001 to S_ORO_T240

NAMELIST /orography_smoothing/ (INPUT_OROSMOOTH)

Parameter	Type	Default	Unit	Description
lfilter_oro	logical	FALSE		switch for orography smoothing
ilow_pass_oro	integer	0		type of orography smoothing and stencil width
numfilt_oro	integer	1		number of filter applications
eps_filter	real	10		smoothing parameter ("strength" of the filtering)
ifill_valley	integer	1		fill valleys before or after oro smoothing (1: before, 2: after)
rfill_valley	real	0	m	mask for valley filling (threshold value)

Parameter	Type	Default	Unit	Description
ilow_pass_xso	integer	1		type of orography eXtra SmOothing and stencil width (for steep orography)
numfilt_xso	integer	1		number of applications of the eXtra filter
lxso_first	logical	FALSE		eXtra SmOothing before or after orography smoothing (TRUE/FALSE)
rxso_mask	real	0	m	mask for eXtra SmOothing (threshold value)

NAMELIST /radtopo/ (INPUT_RADTOPO)

Parameter	Type	Default	Unit	Description
iradtopo	logical			Switch for radiation corrected topography parameters. Not recommended to use if orographical smoothing is false and smoothing is performed in Int2lm later, because of resulting inconsistencies.
nhoi	integer	24		Number of horizon angles
radius	integer	40000	m	Icon-only: Radial distance considered for computation of horizon
min_circ_cov	integer	1	-	Icon-only: Number of gridcells to be skipped at circumference of circle. A value of 1 considers all points, whereas a value of 5 only consider every fifth point at the circumference. Note that the effect of this switch is dependent on the resolution of the grid as well on the radius choosen.
max_missing	real	0.9	-	Icon-only: Upper limit for fraction of missingness for the horizon parameter. Grid-cells with values above will be set to 0.
itype_scaling	integer	2	-	Icon-only: Power of the caling factor $SIN(horizon-angle)$ applied to the geometric skyview factor to account for the anisotropic nature of longwave radiation.

NAMELIST /scale_separated_raw_data/ (INPUT_SCALE_SEP)

Parameter	Type	Default	Unit	Description
lscale_separation	logical			Switch for scale separation. It can only be used in combination with GLOBE as raw data set.
raw_data_scale_sep_path	character			path to 3 km filtered topography
scale_sep_files	character			filename of 3 km filtered topography

6.4 Land Use data**NAMELIST /lu_raw_data/ (INPUT_LU)**

Parameter	Type	Default	Unit	Description
raw_data_lu_path	character			path to landuse data
raw_data_lu_filename	character			filename of landuse raw data
i_landuse_data	integer			switch to choose a land use raw data set; 1 Globcover2009, 2 GLC2000, 3 GLCC, 4 ECOCLIMAP 5 ESA CCI-LC
l_use_corine	logical	.false.		switch to use corine landuse dataset; only possible if i_landuse_data = 1
ilookup_table_lu	integer			switch to choose a lookup table GLC2000 and GLCC: 1: operational settings of GME (Ritter, 2007) 2: operational settings of COSMO (Heise, 2005) 3: experimental setting, analog to look-up tables of ECOCLIMAP (Asensio 2010) GLOBCOVER 2009: 1: operational settings (Asensio, 2011) 2: experimental settings, analog to look-up tables of ECOCLIMAP (Asensio 2010) ESA CCI-LC: 1: experimental settings (Helmert, 2019)
niles_globcover	integer	6		number of tiles for GLOBCOVER data
ncolumn_tiles	integer			number of columns in tile matrix

NAMelist /glcc_raw_data/ (INPUT_LU)

Parameter	Type	Default	Unit	Description
raw_data_glcc_path	character			path to glcc data
raw_data_glcc_filename	character			filename of glcc raw data
ilookup_table_glcc	integer			switch to choose a lookup table 1: operational settings of GME (Ritter, 2007) 2: operational settings of COSMO (Heise, 2005) 3: experimental setting, analog to look-up tables of ECOCLIMAP (Asensio 2010)

NAMelist /glcc_io_extpar/ (INPUT_LU)

Parameter	Type	Default	Unit	Description
glcc_buffer_file	character			name for glcc buffer file

6.5 Aerosol optical depth**NAMelist /aerosol_raw_data/ (INPUT_AOT)**

Parameter	Type	Default	Unit	Description
-----------	------	---------	------	-------------

Parameter	Type	Default	Unit	Description
raw_data_aot_path	character			path to aerosol raw data
raw_data_aot_filename	character			filename of aerosol raw data
iaot_type	integer	1		index to specify AOD raw data set: 1:Tegen 2:AeroCom 3:MACC-II 4:MACv2 5:CAMS

NAMelist /aerosol.io_extpar/ (INPUT_AOT)

Parameter	Type	Default	Unit	Description
aot_buffer_file	character			name for aerosol buffer file

6.6 Climatological 2m temperature

DICT input_tclim (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_t_clim_path	character			path to T2m climatology data
raw_data_t_clim_coarse	character			filename of coarse T2m climatology data
raw_data_t_clim_fine	character			filename of fine T2m climatology data
it_cl_type	integer			switch to choose between the new and fine (1) and the old and coarse over sea and the fine over land (2) raw data set. Note that the fine data set (1) is topographically corrected.
t_clim_buffer_file	character			name for t_clim buffer file

6.7 NDVI data

DICT input_ndvi (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_ndvi_path	character			path to ndvi raw data
raw_data_ndvi_filename	character			filename of ndvi raw data
ndvi_buffer_file	character			name for ndvi buffer file

6.8 Soil data

NAMelist /soil_raw_data/ (INPUT_SOIL)

Parameter	Type	Default	Unit	Description
isoil_data	integer			switch to choose between the raw soil data, 1: FAO, 2: HWSD, 3:HWSD with terra mapping
ldeep_soil	logical			switch for the deep soil, can only be set to .TRUE. if the top and sub soil are deduced from the HWSD data
raw_data_soil_path	character			path to soil raw data
raw_data_soil_filename	character			filename of soil raw data
raw_data_deep_soil_filename	character			filename of deep soil raw data

NAMELIST /soil_io_extpar/ (INPUT_SOIL)

Parameter	Type	Default	Unit	Description
soil_buffer_file	character			name for soil buffer file
soil_buffer_file_consistent	character			name for soil buffer file after consistency check
soil_output_file_consistent	character			name for soil output file after consistency check

NAMELIST /HWSD_index_files/ (INPUT_SOIL)

Parameter	Type	Default	Unit	Description
path_HWSD_index_files	character			path to HWSD lookup tables
lookup_table_HWSD	character			lookup table to convert soiltype index from global to TERRA soiltype
HWSD_data	character			lookup table to convert the global soiltype in fractions of sand, silt, clay and organic carbon and in bulk density for the topsoil
HWSD_data_deep	character			lookup table to convert the global soiltype in fractions of sand, silt, clay and organic carbon and in bulk density for the subsoil
HWSD_data_extpar	character			parameter used only for development purposes

6.9 Freshwater Lake data**NAMELIST /flake_raw_data/ (INPUT_FLAKE)**

Parameter	Type	Default	Unit	Description
raw_data_flake_path	character			path to flake raw data
raw_data_flake_filename	character			filename of flake raw data

NAMELIST /flake_io_extpar/ (INPUT_FLAKE)

Parameter	Type	Default	Unit	Description
flake_buffer_file	character			name for flake buffer file

6.10 Albedo data**DICT input_alb (namelist.py)**

Parameter	Type	Default	Unit	Description
raw_data_alb_path	character			path to raw albedo data
raw_data_alb_filename	character			filename of the raw albedo data
raw_data_alnid_filename	character			filename of the raw NIR-albedo data
raw_data_aluvd_filename	character			filename of the raw UV-albedo data
ialb_type	integer			switch to indicate albedo type 1:total albedo 2:soil albedo 3:as 1 without NI and UV fields

Parameter	Type	Default	Unit	Description
alb_buffer_file	character			name for the albedo buffer file

6.11 ISA data

DICT input.isa (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_isa_path	character			path to ISA raw data
raw_data_isa_filename	character			filename of ISA raw data
isa_type	integer			type of used ISA data source
isa_buffer_file	character			name for ISA buffer file

6.12 AHF data

DICT input.ahf (namelist.py)

Parameter	Type	Default	Unit	Description
raw_data_ahf_path	character			path to AHF raw data
raw_data_ahf_filename	character			filename of AHF raw data
iahf_type	integer			type of used AHF data source
ahf_buffer_file	character			name for AHF buffer file

6.13 Emissivity parameter

DICT input.emiss (namelist.py)

Parameter	Type	Default	Unit	Description
iemiss_type	integer			switch to choose between full-range (1) and long-wave (2) emissivity data
raw_data_emiss_path	character			path to emissivity parameter raw data
raw_data_emiss_filename	character			filenames of emissivity raw data
emiss_buffer_file	character			name for emissivity parameter buffer file

6.14 ERA parameter

DICT input.era (namelist.py)

Parameter	Type	Default	Unit	Description
iera_type	integer			type of ERA climatology: ERA5 (1) and ERA-I (2)
raw_data_era_path	character			path to ERA raw data
raw_data_era_ORO	character			filenames of ERA ORO raw data
raw_data_era_SD	character			filenames of ERA SD raw data
raw_data_era_T2M	character			filenames of ERA T2M raw data
raw_data_era_SST	character			filenames of ERA SST raw data
era_buffer_file	character			name for era parameter buffer file

6.15 Consistency check**NAMELIST /extpar_consistency_check.io/ (INPUT_CHECK)**

Parameter	Type	Default	Unit	Description
l_use_array_cache	flag	F		flag indicating whether mmap-caching is used (reduced memory consumption, but longer runtime)
netcdf_output_filename	character			filename for netcdf output filename
i_lsm_data	integer			integer switch to choose if an external land sea mask is desired or not. 0: no external land sea mask, 1: use external land sea mask
land_sea_mask_file	character			name of the file which can be used as the external land sea mask.
number_special_points	integer			number of points that should be treated specially (maximal value: 3, if no special treatment is desired choose 0).
lwrite_netcdf	logical	T		flag indicating whether NetCDF output for COSMO grid is desired.
tile_mode	integer	0		if activated tile_mode=1 process output for ICON tile structure
lflake_correction	logical	T		if activated then fr_lake values of grid points next to ocean are set to ocean values the lake depth value is set to undefined. This is the default behavior in EXTPAR version 4.0, but not in DWD EXTPAR version 2.10.

NAMELIST /special_points/ (INPUT_SP.1)

Modifications for Falkenberg.

Parameter	Type	Default	Unit	Description
lon_geo_sp	real	14.115	deg east	longitude coordinate of the special point
lat_geo_sp	real	52.156	deg north	latitude coordinate of the special point
soiltype_sp	real	3.0	-	soiltype of the special point
z0_sp	real	0.03	m	roughness length of the special point
rootdp_sp	real	0.6	m	rooting depth of the special point

Parameter	Type	Default	Unit	Description
plcovmn_sp	real	0.55	1	plant cover minimum of the special point
plcovmx_sp	real	0.8	1	plant cover maximum of the special point
laimn_sp	real	0.5	1	leaf area index minimum of the special point
laimx_sp	real	2.5	1	leaf area index maximum of the special point
for_d_sp	real		1	ground fraction covered by deciduous forest of the special point
for_e_sp	real		1	ground fraction covered by evergreen forest of the special point
fr_land_sp	real		1	fraction land cover of the special point

NAMELIST /special_points/ (INPUT.SP.2)

Modifications for Waldstation.

Parameter	Type	Default	Unit	Description
lon_geo_sp	real	13.954	deg east	longitude coordinate of the special point
lat_geo_sp	real	52.186	deg north	latitude coordinate of the special point
soiltype_sp	real	3.	-	soiltype of the special point
z0_sp	real	0.78	m	roughness lenght of the special point
rootdp_sp	real	0.6	m	rooting depth of the special point
plcovmn_sp	real	0.79	1	plant cover minimum of the special point
plcovmx_sp	real	0.81	1	plant cover maximum of the special point
laimn_sp	real	3.0	1	leaf area index minimum of the special point
laimx_sp	real	4.0	1	leaf area index maximum of the special point
for_d_sp	real		1	ground fraction covered by deciduous forest of the special point
for_e_sp	real		1	ground fraction covered by evergreen forest of the special point
fr_land_sp	real		1	fraction land cover of the special point

NAMELIST /special_points/ (INPUT.SP.3)

Modifications for Lindenberg.

Parameter	Type	Default	Unit	Description
lon_geo_sp	real	14.119	deg east	longitude coordinate of the special point
lat_geo_sp	real	52.205	deg north	latitude coordinate of the special point
soiltype_sp	real	5.	-	soiltype of the special point
z0_sp	real	0.07	m	roughness lenght of the special point

6 Namelist Input for Extpar

Parameter	Type	Default	Unit	Description
rootdp_sp	real	0.6	m	rooting depth of the special point
plcovmn_sp	real	0.5	1	plant cover minimum of the special point
plcovmx_sp	real	0.9	1	plant cover maximum of the special point
laimn_sp	real	0.7	1	leaf area index minimum of the special point
laimx_sp	real	3.3	1	leaf area index maximum of the special point
for_d_sp	real		1	ground fraction covered by deciduous forest of the special point
for_e_sp	real		1	ground fraction covered by evergreen forest of the special point
fr_land_sp	real		1	fraction land cover of the special point